

Funambol Windows Mobile Plug-in  
(for Pocket PC)

# User's Guide

*Version 3.0*  
*September 2006*



## **Important Information**

© Copyright Funambol, Inc. 2006. All rights reserved.

The information contained in this publication is subject to US and international copyright laws and treaties. Except as permitted by law, no part of this document may be reproduced or transmitted by any process or means without the prior written consent of Funambol, Inc.

Funambol, Inc. has taken care in preparation of this publication, but makes no expressed or implied warranty of any kind. Funambol, Inc. does not guarantee that any information contained herein is and will remain accurate or that use of the information will ensure correct and faultless operation of the relevant software, service or equipment.

Funambol, Inc., its agents and employees shall not be held liable for any loss or damage whatsoever resulting from reliance on the information contained herein.

Funambol and Sync4j are trademarks and registered trademarks of Funambol, Inc.

All other products mentioned herein may be trademarks of their respective companies.

Published by Funambol, Inc., 643 Bair Island Road, Suite 305, Redwood City, CA 94063



# Contents

<b>Introduction</b> .....	<b>1</b>
Prerequisites .....	1
<b>Installation</b> .....	<b>2</b>
Obtaining the Software .....	2
Installing the Software .....	3
Configuring the Plug-in .....	4
Uninstalling the Software .....	4
<b>Using the Funambol Windows Mobile Plug-in</b> .....	<b>5</b>
Home Screen .....	5
Main Menu Overview .....	6
File Menu .....	7
Edit Menu .....	8
Help Menu .....	18
<b>Resources</b> .....	<b>19</b>
Related Documentation .....	19
Other Resources .....	19





## Introduction

The Funambol Windows Mobile Plug-in (for Pocket PC) provides synchronization functionality for mobile devices running on Microsoft Windows Mobile. After installing the software on your mobile device, you can synchronize the data on the device with that stored in enterprise data sources, including email, PIM data, and files. This document describes how to install, configure, and use the software.

### Prerequisites

The system requirements for using the software are as follows:

#### Desktop or Portable Computer Used to Install the Plug-in on a Mobile Device

- Microsoft Windows 2000 or XP.
- Microsoft ActiveSync 4.0 or 4.1.

#### Mobile Device

- Microsoft Windows Mobile 4.2 or 5.0.

For information on obtaining Microsoft Windows Mobile and Microsoft ActiveSync, see “Resources” on page 19.



## Installation

The section provides details for obtaining, installing and configuring the software environment.

### Obtaining the Software

The Funambol Windows Mobile Plug-in (for Pocket PC) software is available as follows:

Download Site: [www.funambol.com/opensource/downloads.html](http://www.funambol.com/opensource/downloads.html)

File: `funambol-windowsmobile-plugin-3.0.x.exe`

Size: 2.5 MB

The file contains the following:

- Funambol Windows Mobile Plug-in version 3.0.x
- Funambol libraries for Windows Mobile
- Microsoft VB Runtime for Pocket PC



## Installing the Software

Before proceeding, ensure that Microsoft ActiveSync is installed on your desktop/portable computer. If a previous version of the plug-in is installed on the mobile device, you will uninstall that version before installing the current version (as described below).

1. Connect your mobile device to the desktop/portable computer, e.g., via a USB cable.
2. On the desktop/portable computer, start Microsoft ActiveSync.
3. When ActiveSync recognizes device, the New Partnership windows displays. Select **Guest partnership** and click **Next**.
4. If a previous version of the plug-in is **not** installed on the device, skip to step 6. Otherwise, on the ActiveSync main menu bar, select **Tools > Add/Remove Programs**. The Add/Remove Programs windows displays.
5. In the list box, select the previous version of the plug-in and click **Remove**. A verification dialog box displays. Click **OK**.
6. Run the `funambol-windowsmobile-plugin-3.0.x.exe` file. A dialog box displays, asking permission to install the Funambol libraries in the default application installation directory on the device. Click **Yes**.
7. On the mobile device, verify that the Funambol libraries install without error. When complete, on the desktop/portable computer, click **OK**.
8. A dialog box displays, asking permission to install the Microsoft VB Runtime for Pocket PC in the default application installation directory on the device. Click **Yes**.
9. On the mobile device, verify that the VB Runtime installs without error. When complete, on the desktop/portable computer, click **OK**.
10. A dialog box displays, asking permission to install the Funambol Windows Mobile Plug-in (for Pocket PC) in the default application installation directory on the device. Click **Yes**.
11. On the mobile device, verify that the plug-in installs without error. When complete, on the desktop/portable computer, click **OK**.
12. A dialog box displays, notifying you that the installation is complete. Click **Done**.



## Configuring the Plug-in

To configure the software for your device, perform the following:

1. Start the Funambol Windows Mobile Plug-in (for Pocket PC).
2. Access the communication settings by selecting **Edit > Communication Settings**. Specify the following settings: Funambol Server URL, Username, and Password. For details, see "Communication Settings" on page 8.
3. Choose the sources with which to synchronize, and set the appropriate parameters for each. For details, see "Synchronization Settings" on page 9. Note that default parameters are set on the Funambol server for synchronizing contacts and calendar.

## Uninstalling the Software

To uninstall the software, perform the following.

1. Uninstall the Funambol Windows Mobile Plug-in (for Pocket PC).
2. Uninstall the Funambol libraries for Windows Mobile.
3. Uninstall the Microsoft VB Runtime for Pocket PC.






## Using the Funambol Windows Mobile Plug-in (for Pocket PC)

This section introduces the features of the software.

### Home Screen

When you start the plug-in, the following screen appears:




In the diagram above, items A, B, C, D, F, and G are Windows Mobile features. The Funambol Windows Mobile Plug-in (for Pocket PC) provides the following functionality:

- **Synchronize button (E)** – click to synchronize data using the current settings.
- **Funambol main menu (H)** – access menus for synchronizing, specifying configuration settings, viewing a log file, and quitting the plug-in.

## Main Menu Overview

The Funambol main menu at the bottom of the screen contains the following selections:



The selections perform the following actions:

Selection	Action
File > Synchronize	Synchronizes data using the current settings. This is the same as clicking the Synchronize button.
File > Recover (slow-sync. . .)	Displays a window for choosing a source with which to perform a slow-synchronization.
File > Exit	Exits the plug-in.
Edit > Communication Settings	Displays a window for specifying communication settings.
Edit > Synchronization Settings	Displays a window for specifying synchronization settings.
Edit > Log Settings	Displays a window for specifying log settings.
Help > About	Displays the version number the plug-in.
Help > View log	Displays the contents of the log file.




## File Menu

You use the File menu to initiate a synchronization, or exit the plug-in (**File > Exit**).

### Synchronize


Select **File > Synchronize** to start a synchronization using the current setting; the screen displays as follows:



The Funambol icon (double arrows) appears in the title bar when the synchronization is in progress. You can stop the synchronization by clicking this icon; this action displays a pop-up window that asks you to confirm that you want to stop the synchronization.

### Recover

The **File > Recover (slow-sync)...** selection displays the following window:



Choose the source with which to synchronize by checking the appropriate checkbox. Click **Recover** to start a slow-sync; click **Cancel** to close the window without recovering.


## Edit Menu

You use the Edit menu to access the following settings:

- **Communication Settings** – sets the communication parameters between the server and plug-in.
- **Synchronization Settings** – sets the source to be synchronized, and preferences associated with synchronization with that source.
- **Log Settings** – sets the log level.

## Communication Settings

You access communication settings by selecting **Edit > Communication Settings**. You specify the settings on the window shown below:



The following communication settings are displayed:


Setting	Description
Funambol Server URL	The URL of the synchronization server.
Username	The user ID used to access the database associated with the synchronization server.
Password	The password used to access the database associated with the synchronization server.
Device Id	Read-only display of the device ID, which is sent to the server and used in user device mapping.
Current IP	Read-only display of the device's current IP address.

Click the Windows **OK** button to save the settings; click **Cancel** to close the window without changes.



## Synchronization Settings

You access synchronization settings by selecting **Edit > Synchronization Settings**. You specify the settings on the windows shown below:




The initial synchronization settings window displays the following settings:

Setting	Description
Select the source: <ul style="list-style-type: none"> <li>• Contacts</li> <li>• Calendar</li> <li>• Tasks</li> <li>• Notes</li> <li>• Mail</li> <li>• Files</li> </ul>	Specifies the source with which to synchronize. For the selected source, you specify additional settings by clicking the “. . .” button, which displays the More <source> Settings window (e.g., More Mail Settings). These additional settings are described in subsequent sections.  To the right of each source, the current synchronization type is displayed; the possible types are as follows: <ul style="list-style-type: none"> <li>• <b>None</b> – no sync type defined (i.e., no sync with this source)</li> <li>• <b>Normal</b> – normal type of synchronization</li> <li>• <b>Replace local</b> – replace data on the client with data from the server.</li> <li>• <b>Replace remote</b> – replace data on the server with data from the client.</li> <li>• <b>Update local</b> – update data on the client with data from the server.</li> <li>• <b>Update remote</b> – update data on the server with data from the client.</li> </ul> To change the synchronization type of a source, access the More Settings window for the source.
Encryption	Enables content encryption using the 3DES algorithm (global parameter).
Push Settings	Enable push synchronization and/or polling. For details, see “Push Settings” on page 16.

Click the Windows **OK** button to save the settings; click **Cancel** to close the window without changes.

## More Settings Window for Contacts, Calendar or Tasks

When you click the “. . .” button for a synchronization source, the More Settings window displays. If you select Contacts, Calendar, or Tasks as your synchronization source, the More Settings window displays the settings shown below:



The More Settings window for Contacts, Calendar and Tasks displays the following:

Setting	Description
Synchronization Type	<p>Type of synchronization. The selections for all sources are as follows:</p> <ul style="list-style-type: none"> <li>• <b>Normal</b> – two-way fast synchronization.</li> <li>• <b>Replace Local Data</b> – replaces data on the client with data from the server. LOCAL DATA IS DELETED. When a synchronization is attempted, you receive an alert on the device asking you to confirm the deletion of local data. If you specify No, synchronization is not performed; if you do not respond to the alert within 10 seconds, it defaults to No.</li> <li>• <b>Replace Remote Data</b> – replaces data on the server with data from the client.</li> <li>• <b>Update Local Data</b> – updates data on the client with data from the server (no client modifications sent to server).</li> <li>• <b>Update Remote Data</b> – updates data on the server with data from the client (no server modifications sent to client).</li> </ul>
Remote Name (text field in which the specified string must match the source URI on the server)	<p>Name of the synchronization source (i.e., the URI) on the server. For Contacts, the following strings are provided:</p> <ul style="list-style-type: none"> <li>• <b>scard</b> (SIF format)</li> <li>• <b>card</b> (vCard format)</li> </ul> <p>For Calendar, the following strings are valid:</p> <ul style="list-style-type: none"> <li>• <b>scal</b> (SIF format)</li> <li>• <b>cal</b> (iCalendar format)</li> </ul> <p>For Tasks, this setting currently is not available.</p>




Setting	Description
Synchronization Format	Data format of the synchronization. For Contacts, the selections are as follows: <ul data-bbox="732 321 980 394" style="list-style-type: none"><li>• Use SIF Format</li><li>• Use vCard Format</li></ul> For Calendar and Tasks, the selections are as follows: <ul data-bbox="732 451 1024 527" style="list-style-type: none"><li>• Use SIF Format</li><li>• Use iCalendar Format</li></ul>

Click the Windows **OK** button to save the settings, which are stored in the device registry and used in subsequent synchronizations. Click **Cancel** to close the window without changes.

## More Settings Window for Notes or Files

If you select Notes or Files as your synchronization source, the More Settings window displays the settings shown below:



The More Settings window for Notes or Files displays the following:

Setting	Description
Synchronization Type	<p>Type of synchronization. The selections for either source are as follows:</p> <ul style="list-style-type: none"> <li>• <b>Normal</b> – two-way fast synchronization.</li> <li>• <b>Replace Local Data</b> – replaces the data on the client with the data from the server. LOCAL DATA IS DELETED. When a synchronization is attempted, you receive an alert on the device asking you to confirm the deletion of local data. If you specify No, synchronization is not performed; if you do not respond to the alert within 10 seconds, it defaults to No.</li> <li>• <b>Replace Remote Data</b> – replaces the data on the server with the data from the client.</li> <li>• <b>Update Local Data</b> – updates data on the client with data from the server (no client modifications sent to server).</li> <li>• <b>Update Remote Data</b> – updates data on the server with data from the client (no server modifications sent to client).</li> </ul>






Setting	Description
Remote Name (text field in which the specified string must match the source URI on the server)	Name of the synchronization source (i.e., the URI) on the server. The server is configured with the following default values: for Notes, the default string is <b>snote</b> ; for Files, the default string is <b>briefcase</b> .  To use a different synchronization source (e.g., a different database of notes), you need to create and configure a different source on the server, and specify that string in this setting.
Choose directory	The folder on the device to synchronize with the server. Files in the folder are synchronized; files in subdirectories of the folder are not synchronized. When you click the “. . .” button, a window displays that allow you to navigate to the desired folder on the device.

Click the Windows **OK** button to save the settings; click **Cancel** to close the window without changes.

**NOTE:** The Funambol Windows Mobile Plug-in (for Pocket PC) supports the synchronization of text notes only. While it is possible to save hand-written notes or drawings (as images) on a Pocket PC, these are not supported. When selecting a folder for notes synchronization using the “Choose directory” setting described above, you should ensure that folder only contains text notes. If you use graphic notes, save them in a folder other than that specified for the notes synchronization; otherwise, they could be lost during a synchronization.

### More Settings Window for Mail

If you select Mail as your synchronization source, the More Settings window displays the settings shown below:



The More Settings window for Mail displays the following:

Setting	Description
Synchronization Type	Type of synchronization. The selections are as follows: <ul style="list-style-type: none"> <li>• <b>Normal</b> – two-way fast synchronization.</li> <li>• <b>Replace Local Data</b> – replaces the data on the client with the data from the server. LOCAL DATA IS DELETED. When a synchronization is attempted, you receive an alert on the device asking you to confirm the deletion of local data. If you specify No, synchronization is not performed; if you do not respond to the alert within 10 seconds, it defaults to No.</li> </ul>
Remote Name (text field in which the specified string must match the source URI on the server)	Name of the synchronization source (i.e., the URI) on the server. The server is not configured with a default source. You need to create and configure a source on the server before synchronization, and specify that string in this setting.



Click the Windows **OK** button to save the settings, or click **Cancel** to close the window without changes. You can specify additional settings by clicking the **Folders**, **Filters**, or **Account** buttons; see the descriptions for those settings on the next table.


When you click the **Folders**, **Filters**, or **Account** buttons, you can specify the following settings:

Button	Description
Folders	Specify the folder(s) on the device to synchronize by selecting the desired checkbox. Files in the specified folder are synchronized; files in subdirectories of the folder are not synchronized.
Filters	<p>The listboxes contain selections for specifying the parts of a message to download (i.e., header, body, attachments), and the total amount of data to download:</p> <ul style="list-style-type: none"> <li>• <b>Get full messages</b> – download body and attachments. When selected, you can specify the total amount of data to download in the listbox to the right.</li> <li>• <b>Get header and body</b> – download body only. When selected, you can specify the total amount of data to download in the listbox to the right.</li> <li>• <b>Get header only</b> – do not download message data. When selected, the listbox to the right is disabled.</li> </ul> <p><b>Download mail since</b> – select this checkbox to specify filtering based on the age of the message on the device.</p>
Account	<p><b>Display name</b> – the name that is displayed for the account.</p> <p><b>Email address</b> – the email address of the account.</p>

After specifying settings on these windows, click the Windows **OK** button to save the settings; click **Cancel** to close the window without changes. Either of these actions returns you to the More Mail Settings window.

### Push Settings

You access push settings by selecting **Edit > Synchronization Settings > Push Settings**. You specify the settings on the window shown below:



The Push Settings window displays the following:

Setting	Description
Server push	<p>The device sends the IP address it is using to the server. If the server receives and can use the IP address for server-alerted notifications, it sends a successful response, and the device starts listening for notifications.</p> <p>When new mail arrives for the user, the server sends notification, and the client start a sync with the parameters set by the server.</p> <ul style="list-style-type: none"> <li>• <b>Notification type</b> – SMS or TCP/IP</li> <li>• <b>Port</b> – the port on which the device listens for notifications.</li> <li>• <b>Ask Confirmation</b> – specifies whether to ask for confirmation before performing a synchronization. Yes = when a message is ready on the server, and the client is notified, the user receives an alert asking to confirm the synchronization. No = synchronization performed automatically.</li> </ul>
Email polling	<p>Send an email synchronization request to the server at the specified interval. Used when a mobile operator does not give a public IP address.</p>


Click the Windows **OK** button to save the settings; click **Cancel** to close the window without changes.

**NOTE:** You can select both the **Server push** and **Email polling** settings. In this case, the latter will be used when the former is unavailable.



## Log Settings

You access log settings by selecting **Edit > Log Settings**. You specify the settings on the window shown below:



The following log settings are displayed:

Setting	Description
None	No data stored in the log file.
Info	Informational data stored in the log file.
Debug	Debug data stored in the log file.

When set to Info or Debug, the file contains the log only for the last synchronization. Click the Windows **OK** button to save the settings; click **Cancel** to close the window without changes.




## Help Menu

You use the Help menu to access the following:

- **About** – displays information about the software.
- **View log** – displays the log file.


### About

You access information about the software by selecting **Help > About**, as shown below:



### View log

You access the log file by selecting **Help > View log**, as shown below:



This selection opens the log file in Pocket Word.



## Resources

This section lists resources you may find useful.

### Related Documentation

This section lists documentation resources you may find useful.

#### Funambol DS Server Documentation

The following documents form the Funambol DS Server documentation set:

- *Funambol DS Server Architectural Overview*: Read this document for an overview of the architecture.
- *Funambol DS Server Administration Guide*: Read this guide to gain an understanding of installation, configuration, and administration.
- *Funambol DS Server Developer's Guide*: Read this guide to understand how to develop extensions to the server.
- *Funambol DS Server SyncSource API*: Read this reference guide for information on the SyncSource interface and related classes.
- *Funambol DS Server Quick Start Guide*: Read this guide to install and run a simple demonstration of synchronizing PIM data using the Funambol DS Server.
- *Funambol DS Server Module Development Tutorial*: Read this tutorial for instructions on packaging, installing and testing modules.

### Other Resources

This section lists other resources you may find useful.

- For information on Microsoft Windows Mobile, visit <http://www.microsoft.com/windowsmobile/default.aspx>.
- For information on Microsoft ActiveSync, visit <http://www.microsoft.com/windowsmobile/activesync/default.aspx>.